

- **Laboratory for Atmospheric Research Package**

Version 0.2b

- **Overview**

larpkg is a collection of Igor Pro functions focusing on time series, atmospheric fluxes, meteorological parameters, and handling of a few less common scientific data formats. While some functions are decidedly narrow in focus, many are general and would be useful in other contexts. Most higher-level functions come with a host of optional arguments - it's usually worth your time to know what they do!

- [Installation](#)
- [Additional Resources](#)
- [Function Groups](#)
 - [Bitwise Functions](#)
 - [Files and Folders](#)
 - [Igor Functions](#)
 - [Interval Operands](#)
 - [Statistics/Math](#)
 - [Time Functions](#)
 - [Truth Tests](#)
 - [Wind Statistics](#)
- [Menu Additions](#)
- [Graphical User Interfaces](#)
- [LAR Package Reference](#)

- **Installation**

larpkg is available as a compressed archive (.7z or .zip) which can be extracted using your favorite file archive utility. The archive directory structure looks like this:

```
larpkg-<version>.7z\
```

```
  bin\
```

```
      cmdutils\
```

Collection of open-source Windows utilities

```
      ...
```

```
      7zip920.exe
```

Installation binary for open-source archive utility 7-zip version 9.2

```
  larpkg Help.ihf
```

This help file, compiled for use with Igor Pro

```
  larpkg Help.pdf
```

This help file, printed to PDF/A format for reading without Igor Pro

```
  larpkg.ipf
```

Procedure file containing core function set

```
  licenses.txt
```

Relevant licensing for the release

Additionally, you should be able to attain the help file and procedure file as standalone files.

Dependencies

The following procedure files are activated by larpkg because they possess functionality it depends on. It is not necessary to install these files -- they are included with Igor Pro.

- RemovePoints (WaveMetrics Procedures:Data Manipulation:)

Licensing

This information is available in the file `licenses.txt` in the packaged distributions.

- larpkg is covered by the MIT license, <http://mit-license.org/>
- CmdUtils is covered by the GNU General Public License version 2 (GPLv2), <http://www.gnu.org/licenses/gpl-2.0.html>
- 7-Zip is covered by the GNU Lesser General Public License version 2.1 (LGPL), <http://www.gnu.org/licenses/old-licenses/lgpl-2.1.html>; 7z.dll is also covered by the unRAR restriction. Details at <http://www.7-zip.org/license.txt>.

Temporary Install

Opening the procedure files and selecting 'Macros > Compile' is sufficient to use the functions in larpkg. Be aware, however, that if you write procedures which use functions from larpkg and fail to reopen the procedure file next time the experiment is opened, your procedure will not compile until the relevant larpkg procedure file is opened as well.

Per-experiment Install (Adoption)

There are several reasons you might want to use this package on a per-experiment basis, for example:

- You rarely use larpkg but remembering to load it with certain experiments is a pain
- You frequently share experiments with users who do not have/want larpkg permanently installed
- You explicitly archive all procedures (perhaps for auditing purposes) and do not want any ambiguity introduced by using linked files or do not want to track and archive specific versions of larpkg.
- You have made changes to larpkg for use with a specific experiment and do not want to retain those changes otherwise.

To achieve a standalone or per-experiment installation, open the procedure file and give it active focus either by clicking on it or selecting it from 'Windows > Procedure Windows', then select 'File > Adopt Procedure'. More information about this is provided in the help topic [Adopting a Procedure File](#).

Permanent

If you intend to use larpkg frequently and would prefer it open automatically each time Igor Pro loads, it can be installed as a 'global' procedure file. First, extract the archive somewhere. The location is not very important although network users may find it advantageous to store one shared copy on the network instead of several across workstations. Place a shortcut/alias to the extracted archive directory in the "WaveMetrics/Igor Pro User Files/Igor Procedures" folder inside your user's Documents directory. See help topics [Global Procedure Files](#) and [Igor Pro User Files](#) for more information.

Additional Resources

Don't overlook the fact that Igor Pro doesn't have everything activated upon installation! These resources are listed for informational purposes only and do not constitute endorsement of any particular package.

Other built-in functions

Some of the other built-in packages you may want to activate include:

- RosePlot (WaveMetrics Procedures:Graphing:)
- New Polar Graphs (WaveMetrics Procedures:Graphing:New Polar Graph Procedures:)
- VDT, for Data Logger package (More Extensions:Data Acquisition)
- WildPoint (More Extensions:Data Analysis:)
- MLLoadWave (More Extensions:File Loaders:)
- TDM, for loading LabView files (More Extensions:File Loaders:)

- IgorThief, for extracting data from scanned graphs (WaveMetrics Procedures:File Input Output:)

Third-party extensions and snippets

WaveMetrics maintains an online repository of packages, the IgorExchange (igorexchange.com), where users can exchange code snippets and full-blown packages.

Some interesting projects/snippets include:

- DAQ Procedures -- GPIB, NIDAQmx, traditional NIDAQ, serial port, and VISA
- easyHTTP -- Connectivity to the internet, http/ftp/etc
- Time-Frequency Toolkit -- For investigating time-frequency domain of time series
- ADWU 1.0.ipf -- Download weather data based on airport codes (requires easyHTTP)
- Progress window.ipf -- Display a pop-up progress window for long computations
- simple_spectral.ipf -- functions for spectra-related computations

• **Function Groups**

This section provides a broad overview of available functions by group.

Bitwise Functions

There are several functions designed to make bitwise operations more clear. The relevant Igor help topic is [Using Bitwise Operators](#). Reading specific flags from an instrument's diagnostic code is one example of where these functions could be applied.

[BitString](#), [ClearBit](#), [SetBit](#), [ShiftBit](#), [TestBit](#)

Files and Folders

This group includes functions to load and export data from a variety of common formats, as well as to manipulate the underlying file system to make handling data files easier. A utility to load waves from compressed archives without manually extracting them is under development, too.

[BaleWaves](#), [ListFilesIn](#), [LoadCSI](#), [LoadDLT100](#), [LoadG1103](#), [LoadG2301](#), [LoadNMEA](#), [PromptForFileList](#), [UnzipArchive](#), [UnzipArchivesInList](#)

Igor Functions

These functions came about to accomplish some specific, but universal kind of task in Igor Pro.

[AllFoldersHere](#), [AllWavesHere](#), [BatchRemoveNans](#), [CountNans](#), [MinFieldWidth](#), [NewDataFolderX](#), [PromptChooseFolder](#), [RemoveBlanks](#), [StringFromMaskedVar](#)

Interval Operands

The interval operators are intended for analyzing time series in consecutive, adjacent, identically sized subintervals. Sliding windows are not currently available, nor are they planned. The basic options are interval size, in seconds, and aligned/not aligned from midnight with respect to interval size.

With an interval of 30min and initial timestamp of 10:48:24, then if

- aligned is zero, the first output period starts at 10:48:24
- aligned is non-zero, the first output period starts at 10:30:00

In general, results are provided as a wave reference; see [Free Waves](#). This puts the onus on the user to explicitly save their results using [Duplicate](#) or [MoveWave](#). A few more complex functions both modify source waves and return results; this is made explicit in the reference when true.

[IntervalBoundaries](#), [IntervalCov](#), [IntervalDespikeHaPe](#), [IntervalECLatentHeat](#), [IntervalECSensibleHeat](#), [IntervalEC_WPL80](#), [IntervalFrictionVelocity](#), [IntervalMaxPntsGone](#), [IntervalMean](#), [IntervalObukhovLength](#), [IntervalSdev](#), [IntervalTimestamps](#), [IntervalTKE](#), [IntervaluvwRotation](#), [IntervalWindDirMardiaSdev](#), [IntervalWindDirScalarMeanSdev](#), [IntervalWindDirUnitVectorMean](#), [IntervalWindDirVectorMean](#),

[IntervalWindDirYamartinoSdev](#), [IntervalWindSpeedScalarMean](#), [IntervalWindSpeedScalarHMean](#),
[IntervalWindSpeedScalarSdev](#), [IntervalWindSpeedVectorMean](#), [IntervalWindSpeedPersist](#)

Statistics/Math

These supplement the built-in math and statistics functions.

[BankerRound](#), [Cov](#)

Time Functions

Time is a very important consideration. It can make up to half of the data.

[IsntChronological](#), [serial2secs](#), [string2secs](#), [TimeIntervalBoundaries](#), [TimeRegex](#)

Truth Tests

These functions all return the true/false truth of some specific condition.

[HasDuplicateDFRefs](#), [HasDuplicateWRefs](#), [HasNans](#), [NotAllSameLength](#), [SameNumPnts](#),
[SameXscaling](#)

[HasDuplicateDFRefs](#), [HasDuplicateWRefs](#), [HasNANs](#), [SameNumCols](#), [SameNumChunks](#),
[SameNumLayers](#), [SameNumPnts](#), [SameNumRows](#), [SameXscaling](#), [NotAllSameLength](#)

Wind Statistics

These functions handle some of the basic wind data reduction routines and provide a few convenient conversions.

[Cardinal2D](#), [D2Cardinal](#), [D2R](#), [ModWD](#), [R2D](#), [WindDir](#),
[WindDirMardiaSdev](#), [WindDirScalarMeanSdev](#), [WindDirUnitVectorMean](#), [WindDirVectorMean](#),
[WindDirYamartinoSdev](#), [WindSpeed](#), [WindSpeedScalarMean](#), [WindSpeedScalarHMean](#),
[WindSpeedScalarSdev](#), [WindSpeedVectorMean](#), [WindSpeedPersist](#)

- **Menu Additions**

In addition to functions, several useful menus are added:

- Under Data > Load Waves, there are links to guided file loading interfaces
- A new submenu More Tools is added to Analysis
- The plot context-menu is expanded with useful scaling options

- **Graphical User Interfaces**

These functions handle some of the basic wind data reduction routines and provide a few convenient conversions.

[ListFilesIn_Panel](#), [LoadLGR_Panel](#), [PromptedLoadCSI](#), [PromptedLatLongDistance](#)

=====

- **LAR Package Reference**

AddWaveRef(*addref*, *wrefs*, *beforePoint*)

Returns *wrefs* after inserting wave reference *addref* at point *beforePoint*; remaining points are shifted.

See Also:

[InsertPoints](#), [WAVE References](#)

AllDataFoldersHere(*sortBy*)

Returns wave of data folder references to all data folders in the current data folder, sorted according to the value of *sortBy*. All folders named *Packages* are omitted.

type is a literal number which controls the sorting method:

-1: No sort (effectively sorts by creation date)

0: Default sort (ascending case-sensitive alphabetic ASCII sort)

1: Descending sort

2: Numeric sort

4: Case-insensitive sort

8: Case-sensitive alphanumeric sort using system script

16: Case-insensitive alphanumeric sort that sorts wave0 and wave9 before wave10.

or a bitwise combination of the above with the following restriction: only one of 2, 4, 8, or 16 may be specified. The legal values are thus -1, 0, 1, 2, 3, 4, 5, 8, 9, 16, and 17. Other values will produce undefined sorting criteria.

Examples

```
function baz()
    wave/DF w = AllFoldersHere()
    variable i
    for (i=0; i<numpts(w); i+=1)
        print i, DataFolderDir(2, w[i])
    endfor
end
```

See Also:

[SortList](#), [AllWavesHere](#)

AllWavesHere(*sortBy*)

Returns wave of references to all waves in the current data folder, sorted according to *sortBy*, which is a literal number controlling the sorting method:

-1: No sort (effectively sorts by creation date)

0: Default sort (ascending case-sensitive alphabetic ASCII sort)

1: Descending sort

2: Numeric sort

4: Case-insensitive sort

8: Case-sensitive alphanumeric sort using system script

16: Case-insensitive alphanumeric sort that sorts wave0 and wave9 before wave10.

or a bitwise combination of the above with the following restriction: only one of 2, 4, 8, or 16 may be specified. The legal values are thus 0, 1, 2, 3, 4, 5, 8, 9, 16, and 17. Other values will produce undefined sorting criteria.

See Also:

[WaveList](#), [SortList](#), [WAVE References](#)

AmbientTemp(*Ts*, *Q_*)

ThreadSafe

Return ambient temperature in Celcius, derived from sonic anemometer/thermometer measurement *Ts* and ambient specific humidity *Q_*. Function does internal conversion to perform calculation in Kelvin.

BaleWaves(*tstamp*, *refw*, *interval*, *options*, *formatTableName*, *destNameMask*, *destPath*)

The BaleWaves function writes each subinterval of the waves included in *refw* to a comma separated file. One file is generated for each interval.

****this documentation needs review!****

Parameters

tstamp is a double precision wave of sequential timestamps. It should not contain any empty values (NaN).

refw is a wave of wave references to include in the output file. If a timestamp column is desired, then *tstamp* should also be the first element of *refw*. The order of *refw* determines left-to-right order of columns in the output file.

interval is the length, in seconds, of each output file.

options is a literal number representing various bit combinations of:

Bit #	Bit Value	Option
-------	-----------	--------

1

formatTableName is a string containing the name of an existing table which reflects the desired formatting for each column. Formatting is copied according to column number so the order in this table should be the same as in *refw*.

destNameMask is a string file name mask following the same field code conventions as [StringFromMaskedVar](#). A file extension should be included since none is appended. If no field code is used to distinguish output files, it is likely each file will overwrite the last and only the final file will remain.

destPath is a string containing a fully-qualified path to the desired output directory, or an empty string ("") to cause a prompt.

Details

The order of columns is determined by the order of waves in *refw*. The formatting of each column is copied from an existing table named *formatTableName*. If the table is not found, then -1 is returned.

The size of the interval is specified, in seconds, by *interval*. If *aligned* is nonzero, then intervals will start/stop on whole multiples of the interval counting from midnight; the default (0) is to start/stop relative to the value of *tstamp*[0].

If *overwrite* is a positive non-zero value, files with conflicting names **will be overwritten** without prompt. A value of zero will result in a Save As.. prompt if file names conflict. Negative non-zero values are reserved for future use.

See Also:

[SaveTableCopy](#), [SaveData](#), [Save](#), [Tables](#)

BankerRound(*inVal*, *place* [, *toOdd*])

Rounds a numerical expression *inVal* to decimal column represented by 10^{place} using round-to-even rules. A nonzero value for optional parameter *toOdd* will cause round-to-odd behavior instead, if desired.

Details

Under normal conventions, the remainder one-half (0.5) is rounded upwards to the next whole number but this operation is not symmetric and such rounding can introduce an upwards bias, especially in large data sets. One solution is to round one-half towards the nearest even integer, resulting in equal probabilities the rounding will occur upwards versus downwards.

This is the default rounding mode used in IEEE 754 computing functions and operators.

Examples

```
foovar = BankerRound(foovar, 0) // round to integer (10^0=1s)
foovar = BankerRound(foovar, 3) // round to thousands (10^3=1000s)
wave0 = BankerRound( wave0[p], 3) // round whole wave to thousands
```

References

Rounding https://secure.wikimedia.org/wikipedia/en/wiki/Banker%27s_rounding

See Also:

[round](#), [trunc](#), [floor](#), [ceil](#)

BitString(*var*, *howMany* [, *maxLen*])

Returns a string representation of *howMany* bits in *var*, starting with the least significant bit, written from right to left in 4 digit groups.

Details

Since bitwise operations only make sense on integers, *var* is treated as one.

The default behavior is to limit *howMany* to between 1 and 32 bits. Since most variables cannot hold more information, this makes sense but the optional parameter *maxLen* is provided as a way to bypass this if desired.

Examples

```
print WriteBits(21, 8)      // 0001 0101
print WriteBits(3021, 8)   // 1100 1101
print WriteBits(1+2+4, 4)  //      0111
print WriteBits(1+2+4, 6)  //      00 0111
```

See Also:

[Using BitWise Operators](#), [ClearBit](#), [SetBit](#), [ShiftBit](#), [TestBit](#)

Cardinal2D(*inStr*)

Returns numeric interpretation of cardinal wind direction (NW, S, SSE) in string *inStr* or returns NAN if *inStr* is not understood.

Details

The comparison to *inStr* is done case-insensitive with trailing spaces removed. Acceptable combinations of cardinal wind direction include, going clockwise:

N, NNE, NE, ENE, E, ESE, SE, SSE, S, SSW, SW, WSW, W, WNW, NW, NNW

Tip

This function can be used effectively in a wave assignment:

```
Make/N=(numpts(cardWD)) numWD = Cardinal2D(cardWD[p]) // one fell swoop
```

See Also:

[D2Cardinal](#), [D2R](#), [R2D](#), [Wave Assignment](#)

ClearBit(*var*, *bit*)

Returns *var* with bit number *bit* set to zero. Bit numbering is zero-indexed.

Details

Since bitwise operators only make sense on integers, *var* is treated as one and an integer is returned.

This is basically a wrapper for the bitwise complement (~) followed by the bitwise AND (&). It was derived from the example under [Using Bitwise Operators](#).

See Also:

[SetBit](#), [ShiftBit](#), [TestBit](#), [BitString](#)

ConcatAcrossDFRs(*DFRlist*, *destPath*, *overwrite*, *kill*, [*wfilter*])

Returns

See Also:

[???](#)

CountNans(*theWave*)

Returns the total number of NANs in *theWave*.

See Also:

[NAN](#), [numtype](#)

Cov(*wx*, *wy* [, *p1*, *p2*])

Returns the covariance of waves *wx* and *wy*. If these waves are different lengths or contain empty values (NANs) then NAN is returned. The covariance is computed as

$$Cov(\vec{w}x, \vec{w}y) = \overline{wx' \cdot wy'} - \overline{wx} \cdot \overline{wy}$$

A point subrange may be specified using optional parameters *p1* and *p2*.

See Also:

[IntervalCov](#), [Mean](#), [Variance](#)

D2Cardinal(*inVal*)

Returns string containing the nearest cardinal wind direction (NW, S, SSE) to *inVal*, which is wrapped into the range of $0 \leq inVal < 360$. Valid output wind directions include:

N, NNE, NE, ENE, E, ESE, SE, SSE, S, SSW, SW, WSW, W, WNW, NW, NNW

Tip

This function could be used effectively in a wave assignment:

```
Make/N=(numpnts(WD)) labels = D2Cardinal( WD[p] )      // maybe for a graph
```

See Also:

[Cardinal2D](#), [D2R](#), [R2D](#), [Wave Assignment](#)

D2R(*inVal*)

ThreadSafe

Returns *inVal* after converting from degrees to radians. Useful in wave assignments.

See Also:

[R2D](#), [Cardinal2D](#), [D2Cardinal](#), [Wave Assignment](#)

daqfactory2secs(*timeval*)

ThreadSafe

Returns DAQFactory (TM) timestamps converted to Igor date/time value

See Also:

[date2secs](#)

DayOfWeek(*tstamp*)

Returns day of the week (1=Sunday,...,7=Saturday) based on Igor date/time value.

See Also:

[????](#)

DensityOfAir(*T_*, *P_*, [, *inMoles*])

Returns density of air in g/m³ or, if *inMoles* is non-zero, mol/m³ using ideal gas law.

[more detail here](#)

See Also:

[????](#)

DespikeHaPe(...)

Performs 'soft' spike despiking routine.

[more detail here](#)

See Also:

[????](#)

DewPoint(*e_*)

Returns dew point based on vapor pressure.

[more detail here](#)

See Also:

[????](#)

DiagnoseCPC3776(*diagWord, option*)

Creates boolean waves denoting presence or absence of diagnostics flags.

[more detail here](#)

See Also:

[????](#)

DiagnoseCSAT3(*diagWord, option*)

Creates boolean waves denoting presence or absence of diagnostics flags.

[more detail here](#)

See Also:

[????](#)

DiagnoseLI7500(*diagWord, option*)

Creates boolean waves denoting presence or absence of diagnostics flags.

[more detail here](#)

See Also:

[????](#)

DielAverage(*wname, tstamp, mode*)

Computes means over 24-hour periods. No internal nan handling.

[more detail here](#)

See Also:

[????](#)

doy2sec(*doy, year*)

Converts a decimal day-of-year into Igor date/time value.

[more detail here](#)

See Also:

[????](#)

ECLatentHeat(*h2o, w_ [, T_, p1, p2]*)

Unverified

Return latent heat flux using eddy covariance.

[more detail here](#)

See Also:

[????](#)

ECSensibleHeat(T_- , w_- , P_- , Q_- [, $p1$, $p2$])

Unverified

Return sensible heat flux in W/m^2 using eddy covariance.

[more detail here](#)

See Also:

[????](#)

EC_WPL80($meanRHOc$, $meanRHOv$, $meanRHOd$, $meanT$, cov_w_rhoV , cov_w_T)

Unverified

Return eddy covariance density corrections according to Webb, Pearman, Leuning (1980).

[more detail here](#)

See Also:

[????](#)

EC_WPL80_TS(ρC , ρV , ρD , T_- , w_- [, $p1$, $p2$])

Unverified

Return eddy covariance density corrections for a time series according to Webb, Pearman, Leuning (1980).

[more detail here](#)

See Also:

[????](#)

EstimateLag($baseWave$, $targetWave$, $keepResults$)

Returns estimate of record lag between two waves or NAN for error.

[more detail here](#)

See Also:

[????](#)

excel2secs($serialdate$ [, $use1904mode$])

ThreadSafe

Converts "serial date" used by Microsoft Excel (TM) into Igor date/time value.

[more detail here](#)

See Also:

[????](#)

FlattenDir($pathName$, $recurse$, $overwrite$ [, $fileFilter$, $kill$])

Flattens file directories by recursively lifting contents out of subfolders.

[more detail here](#)

See Also:

[????](#)

FrictionVelocity(u_- , v_- , w_- [, $p1$, $p2$])

Returns friction velocity following the AMS definition.

[more detail here](#)

See Also:

[????](#)

GetDataFolderList(*[seePkgs]*)

Returns sorted, hierarchal list of all datafolders

[more detail here](#)

See Also:

[????](#)

HasDuplicateDFRefs(*dfrefs*)

Returns the element number of the first duplicate data folder reference in wave *refw*. If no duplicates are found, 0 is returned.

See Also:

[DataFolderRefsEqual](#)

HasDuplicateWRefs(*wrefs*)

Returns the element number of the first duplicate wave reference in wave *refw*. If no duplicates are found, 0 is returned.

See Also:

[WaveRefsEqual](#)

HasNans(*wname*)

Returns the element number of the first NAN found in *wname* or 0 if none are found. The special case of *wname[0]* = NAN returns -1.

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

HaveNans(*wrefs* [, *p1*, *p2*])

Returns the element number of the first NAN found in *wname* or 0 if none are found. The special case of *wname[0]* = NAN returns -1.

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

IntervalBoundaries(*tstamp*, *interval*, *aligned*)

Returns a wave describing the starting point of each subinterval of length *interval* in *tstamp*. If *tstamp* has empty fields or out-of-order elements, NAN is returned.

Parameters

tstamp is a double-precision wave, ordered chronologically, without empty fields (NaNs)

interval is the length of subinterval, in seconds

If *aligned* is zero, the first subinterval begins at the value of *tstamp[0]* and the following subintervals start at *tstamp[0]+interval * n* where *n* increments for each following interval. If *aligned* is nonzero, subintervals start on whole multiples of the interval starting from the previous midnight.

Details

The wave *tstamp* is checked to ensure chronological order; if it fails this check, the value NAN is returned.

The lower boundary of the first interval is taken as *tstamp[0]*. If *aligned* is nonzero, the upper boundary of the first interval is set to the next whole multiple of *interval* after the lower boundary; otherwise, the upper boundary is the lower boundary plus *interval*. Values in *tstamp* are compared to the upper boundary and when the next row value is \geq upper boundary (or doesn't exist, ie. end of wave), the row corresponding to the lower boundary is recorded. The lower boundary is then set equal to the upper boundary, the upper boundary is recomputed and the procedure continues.

Examples

```
Function seehalfhours()
    wave timestamp
    wave/D w = TimeIntervalBoundaries(timestamp, 30*60, 1)
    variable i
    for (i=0; i<DimSize(w,0); i+=1)
        string t1 = secs2time(timestamp[ w[i][%lo] ],3,1) // to fit on 1 print line
        string t2 = secs2time(timestamp[ w[i][%hi] ],3,1)
        print/D "Interval",i,"Points",w[i][%lo],"-",w[i][%hi],"Time",t1,"-",t2
    endfor
End
```

Which produces output similar to:

```
Interval 0 Points 0 - 13043 Time 12:08:15.6 - 12:29:59.9
Interval 1 Points 13044 - 31043 Time 12:30:00.0 - 12:59:59.9
Interval 2 Points 31044 - 49043 Time 13:00:00.0 - 13:29:59.9
...
Interval 525 Points 9445044 - 9463043 Time 10:30:00.0 - 10:59:59.9
Interval 526 Points 9463044 - 9481043 Time 11:00:00.0 - 11:29:59.9
Interval 527 Points 9481044 - 9490026 Time 11:30:00.0 - 11:44:58.2
```

See Also:

[some other function](#)

IntervalCov(*wx*, *wy*, *tstamp*, *interval*, *aligned* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalDespikeHaPe(*wname*, *tstamp*, *interval*, *aligned* [, *multiplier*, *increment*, *passes*, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalECLatentheat(*h2o*, *w_*, *tstamp*, *interval*, *aligned* [, *T_*, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalECSensibleHeat(*T_*, *w_*, *P_*, *Q_*, *tstamp*, *interval*, *aligned* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalEC WPL80(*rhoC*, *rhoV*, *rhoD*, *T_*, *w_*, *tstamp*, *interval*, *aligned* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalFrictionVelocity(*u_*, *v_*, *w_*, *tstamp*, *interval*, *aligned* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalMaxPntsGone(*wrefs*, *tstamp*, *interval*, *aligned* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalMean(*wname*, *tstamp*, *interval*, *aligned* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalObukhovLength(*u_*, *v_*, *w_*, *Tv*, *tstamp*, *interval*, *aligned* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalSdev(*wname*, *tstamp*, *interval*, *aligned* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalTimestamps(*tstamp*, *interval*, *aligned*, *edge* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalTKE(*u_*, *v_*, *w_*, *tstamp*, *interval*, *aligned* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervaluvwRotation(*uvwMatrix*, *type*, *tstamp*, *interval*, *aligned* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalWindDirMardiaSdev(*Ux*, *Uy*, *tstamp*, *interval*, *aligned* [, *bp*])

This is a subtopic.

See Also:

[Another Topic](#)

IntervalWindDirScalarMeanSdev(*Ux, Uy, azimuth, flag, tstamp, interval, aligned [, bp]*)

This is a subtopic.

See Also:

[Another Topic](#)

IntervalWindDirUnitVectorMean(*Ux, Uy, azimuth, tstamp, interval, aligned [, bp]*)

This is a subtopic.

See Also:

[Another Topic](#)

IntervalWindDirVectorMean(*Ux, Uy, azimuth, flag, tstamp, interval, aligned [, bp]*)

This is a subtopic.

See Also:

[Another Topic](#)

IntervalWindDirYamartinoSdev(*Ux, Uy, tstamp, interval, aligned [, bp]*)

This is a subtopic.

See Also:

[Another Topic](#)

IntervalWindSpeedScalarMean(*Ux, Uy, tstamp, interval, aligned [, bp]*)

This is a subtopic.

See Also:

[Another Topic](#)

IntervalWindSpeedScalarHMean(*Ux, Uy, tstamp, interval, aligned [, bp]*)

This is a subtopic.

See Also:

[Another Topic](#)

IntervalWindSpeedScalarSdev(*Ux, Uy, tstamp, interval, aligned [, bp]*)

This is a subtopic.

See Also:

[Another Topic](#)

IntervalWindSpeedVectorMean(*Ux, Uy, tstamp, interval, aligned [, bp]*)

This is a subtopic.

See Also:

[Another Topic](#)

IntervalWindSpeedPersist(*Ux, Uy, tstamp, interval, aligned [, bp]*)

This is a subtopic.

See Also:

[Another Topic](#)**IsntChronological**(*wname*)*ThreadSafe*

Returns the row number of the first element of *wname* to violate chronological order or of the first empty field (NAN), otherwise returns false (0). Special case of *wname*[0]=NAN returns -1.

Examples

```
If ( IsntChronological(timestamp) )
    // fix the wave or complain to user and quit
endif
```

See Also:

[Sort](#), [RemoveNaNs](#), [BatchRemoveNaNs](#)

LatentHeatVapH2O(*T_*)

Returns latent heat of vaporization of water in J/g based on temperature in Celcius.

See Also:

[Another Topic](#)

LatLongDistance(*lat1, long1, lat2, long2*)

Returns distance as-the-crow-flies (Haversine formula) between lat/long pairs 1&2, in meters.

See Also:

[Another Topic](#)

ListFilesIn(*pathName, fileFilter, fileExt, recurse, sortBy*)

The ListFilesIn function returns a semicolon separated list of all the files in *pathName* with extensions matching *fileExt*, optionally searching subfolders and sorting file/folder names.

Parameters

pathName is a string containing the name of an existing path as might be created using [NewPath](#) or choosing Misc.->New Path... from the Igor menus.

fileFilter is a string containing a regular expression which returned file names must match or a zero-length string ("") to match all files. The format of the regular expression is the same as for [Grep](#) and [GrepList](#). See [Regular Expressions](#) for more details.

fileExt is a string, up to four-characters, specifying the extension of the file type to list or "?????" to list all file types. See the *extension* parameter of [IndexedFile](#) for more details.

recurse is a variable indicating maximum level of depth to use while searching subfolders. If its value is zero, no subfolders are searched. A positive integer *n* will result in *n* levels of subfolders being searched in a recursive manner; a negative integer will result in a search of all levels.

sortBy is a variable specifying the sort mode to apply: a value of -1 will sort files and folders according to creation date while other valid values are identical to *options* in [SortList](#).

See Also:

[IndexedFile](#), [IndexedDir](#), [NewPath](#), [SortList](#), [File Types and Extensions](#), [ParseFilePath](#), [Path Seperators](#), [Regular Expressions](#)

ListDataFoldersIn(*folder*)

Recursively searches for data folders in *folder* and returns hierarchal, semicolon-separated list.

See Also:

[Another Topic](#)

LoadCSI(*fileList*, *fileType*, *overwrite*, *convertTS*, *options* [, *baseSFname*])

The LoadCSI function loads data from one or more Campbell Scientific Loggernet files into Igor waves and, optionally, converts string timestamps into their double-precision representation.

If successful, 0 is returned; otherwise, -1 is returned.

Details

The string *fileList* contains a semicolon-separated list of full file paths (as might be returned by [PromptForFileList](#) or [ListFilesIn](#)). Each file is loaded assuming the first column contains quoted timestamps and subsequent columns contain numeric data. Most of the time this is desired since Campbell places quotes around NaNs and a forced numeric load prevents columns beginning with NAN from being interpreted as text. If the data file contains a legitimate text column, such as a log file might, then LoadCSI will not work for your situation.

If the list contains one file, all waves are loaded into the current directory; otherwise, one subfolder will be created in the current directory for each file. Subfolder creation can be forced for a single-item *fileList* using bit 5 of *options*. If subfolders are created, the name of each is derived from a strict cleanup of each file name. In the event many identically-named files are loaded, the name of each file's parent folder can be used instead by setting bit 2 of *options*.

authors note: explore and describe what happens if multiple files are loaded from the same directory and the subfolder names are set to file's parent subfolder. does behavior change in combination with overwrite/skip parameters?

maybe add a convert variable since it's so common to want to do and not quite the same as the subfolder arguments

Using bit 3 of *options* and optional parameter *baseSFname* provides a third, independent method of specifying subfolder names. In this case, each subfolder is given the name returned by [StringFromMaskedVar](#)(*baseSFname*, <*index*>, *fixNNwidth*=<*minWidth*>) where <*index*> is the zero-based index of the current file in *fileList*, <*minWidth*> is automatically set to the shortest necessary field width, and *baseSFname* is, by default, "loadCSI_file\nn".

If you use bit 3 and change *baseSFname*, do not forget to include a field code or the same subfolder name will be generated for each file. Depending on combinations of other settings, this could result in each new file overwriting the last, only the first file loading or some other, undefined behavior.

fileType specifies the file format. Presently, only two file types are supported.

- 0: TOA5: long (4-line) header
- 1: TOAC11: short (2-line) header
- 2: TOB1: table-oriented binary [****not implemented****]
- 3: TOB2: table oriented binary [****not implemented****]
- 4: TOB3: table-oriented binary [****not implemented****]
- 5: CSIXML: extensible markup language [****not implemented****]

If *overwrite* is nonzero, existing subfolders and waves will be overwritten; otherwise, unique names will be used. Setting bit 4 of *options* will cause a file to be skipped if the target subfolder already exists, rather than creating a unique subfolder. This could speed up loading new data into an existing experiment.

options is a bitwise combination controlling several auxiliary options. See [Setting Bit Parameters](#) for details about bit settings.

- Bit 0: 1 Convert loaded timestamps into an Igor date/time wave named "timestamp". Since Campbell Scientific places double-quotes around timestamps, it is not possible to load them directly as Igor date/time values.
- Bit 1: 2 Keep the original string timestamp wave, renamed "timestamp_STR". This bit is

- ignored if Bit 0 is not set.
- Bit 2: 4 Derive subfolder names from file's parent folder name instead of using file's name.
- Bit 3: 8 Derive subfolder names from *baseSFname* and the file's index # in *fileList*. See above and [StringFromMaskedVar](#) for details.
- Bit _: 16 **will be reserved for concatenation method**
- Bit _: 32 **will be reserved for something else**
- Bit 4: 64 Skip existing subfolders instead of generating unique name when *overwrite* is false.
- Bit 5: 128 Force individual files to load in subfolders as if *fileList* contained multiple items.

The above bits may be combined with these exceptions:

- if bit 0 is not set, bit 1 is ignored
- if bit 2 is set, bit 3 is ignored
- if *overwrite* is true, bit 4 is ignored

See Also:

[LoadWave](#), [Setting Bit Parameters](#)

LoadLGR(*fileList*, *modelName*, *overwrite*, *concat*, *resamp*, *options* [, *baseSFname*, *B*])

Reads data file from Los Gatos Research analyzer

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

LoadPicarro(*fileList*, *modelName*, *overwrite*, *concat*, *tsconv*, *options* [, *baseSFname*, *B*])

Reads data file from Picarro trace gas analyzers; only CO2/CH4/H2O (G2301-f) supported right now.

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

MinFieldWidth(*num*)

Returns the minimum number of fields necessary to hold the absolute value of integer *num*.

Examples

```
print MinFieldWidth( 0 )           // 0
print MinFieldWidth( 0.5 )         // 0      fractional portions are ignored
print MinFieldWidth( 2 )           // 1
print MinFieldWidth( -2 )          // 1      negative signs are ignored
print MinFieldWidth( 1000 )        // 4
print MinFieldWidth( 999 )         // 3
print MinFieldWidth( 999.99 )      // 3
```

See Also:

[StringFromMaskedVar](#)

MixingRatio(*C_*, *T_*, *P_*, *h2o* [, *inMass*])

Returns dimensionless molar mixing ratio of constituent C as the ratio of moles of C to moles of dry air. Pass non-zero value to *inMass* to receive mass mixing ratio.

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

MixingRatioMF(*C_*, *T_*, *P_*, *MFw*)

Returns dimensionless molar mixing ratio of constituent C as the ratio of moles of C to moles of dry air.

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

MixingRatioVP(*e_*, *P_* [, *MW*])

Returns dimensionless mass mixing ratio of a vapor as the ratio of mass of vapor to the mass of dry air. Assumes vapor is water; specify molecular weight of alternate vapor using *MW* if desired.

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

ModWD(*inVal*)

Returns *inVal* after adding or subtracting 360 to bring within the range $0 \leq inVal < 360$.

See Also:

[Mod](#)

MoleFraction(*C_*, *T_*, *P_*)

Returns dimensionless mole fraction of constituent C as ratio of moles of C to total moles in system.

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

NewDataFolderX(*destPath*)

Returns a data folder reference to an eXtended folder path specified by string *destPath*. This path can be absolute (from root:) or relative (start with :) and may contain multiple levels separated by a colon (:).

Details

If the folder does not exist it is created, along with all necessary parent folders; if it does exist, it is switched to quietly. Liberal folder names can quoted or unquoted. Pairs of colons are interpreted as 'up directory' so :: refers to a parent and ::: refers to a parent's parent.

Examples

```
SetDataFolder NewDataFolderX("root:Packages:mynewfolder:temp")
DFREF outputDir = NewDataFolderX(":group"+num2istr(grp)+":run"+num2istr(run))
DFREF inputDF = NewDataFolderX($inputStr)
```

See Also:

[Data Folders](#), [Data Folder References](#), [NewDataFolder](#), [SetDataFolder](#)

NewProgressWindow()

Creates a new progress window with 0% progress and returns name of the window.

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

ObukhovLength(*frictionVelocity*, *meanTv*, *cov_w_Tv*)

Returns the Monin-Obukhov length in meters from scalar values.

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

ObukhovLengthTS(*u_*, *v_*, *w_*, *Tv* [, *p1*, *p2*])

Returns the Monin-Obukhov length in meters from a time-series.

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

NotAllSameLength(*refw`*)

Returns the element of the first wave in wave *refw* to have a different length. If all waves are the same length, a 0 is returned.

See Also:

[numpnts](#)

PotentialTemp(*T_*, *P_* [, *P0*])

Returns the potential temperature; standard pressure used is P0 = 1000mb by default.

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

PromptSetDataFolder()

Prompts user to select a datafolder, switches to chosen folder and returns a DFREF to the user's **starting** location. This may be useful if you want to switch back later.

Examples

```
DFREF sav0 = PromptChooseFolder()
// mess with some data
SetDataFolder sav0
```

See Also:

[Data Folder References](#), [SetDataFolder](#), [GetDataFolderDFR](#)

PromptForFileList(*msg*)

Displays an Open File dialog box to user. Returns semicolon separated list of files selected or an empty string ("") if the user cancels. String parameter *msg* is shown in the title bar of the dialog box.

See Also:

[Open](#), [Displaying a Multi-Selection Open File Dialog](#)

R2D(*inVal*)

ThreadSafe

Returns *inVal* after converting from radians to degrees. Useful in wave assignments.

See Also:

[D2R](#), [Cardinal2D](#), [D2Cardinal](#), [Wave Assignment](#)

RelativeHumidity(e_{-} , T_{-})

Returns relative humidity based on ambient temperature in Celcius and water vapor pressure in mbar or hPa.

[more detail here](#)

See Also:

[RemoveNaNs](#), [BatchRemoveNaNs](#)

RemoveBlanks(*theWave*)

ThreadSafe

Removes blank ("") rows in text wave *theWave* and returns the number of rows removed.

This function was inspired by [RemoveNaNs](#) in [<Remove Points.ipf>](#)

See Also:

[RemoveNaNs](#)

RemoveNansW(*wrefs*)

Removes NaNs from waves while preserving correct alignment of values across rows.

Details

Checks each wave in *refw* for NAN values and, if found, removes that row from each wave in *refw*. The operation is performed so the alignment of data values remains consistent. This may be an important consideration when preparing sets of XY data for operations which do not accept NAN (such as [Mean](#)).

See Also:

[RemoveNaNs](#)

RemoveWaveRef(*remref*, *wrefs*)

Remove any references in *wrefs* which are equivalent to *remref*.

See Also:

[????](#)

ReplaceWaveValues(*wrefs*, *withVal*, *mode*, *val1*, *val2* [, *p1*, *p2*])

[need description](#)

See Also:

[????](#)

ResampleXY(*tstamp*, *wrefs*, *newRate*)

[need description](#)

See Also:

[????](#)

SameNumCols(*w1*, *w2*)

ThreadSafe

Returns truth or falsehood of whether waves *w1* and *w2* have equal number of columns.

See Also:

[numpnts](#)

SameNumColsW(*wrefs*)

ThreadSafe

Returns truth or falsehood of whether all waves in *wrefs* have equal number of columns.

See Also:

[numpnts](#)

SameNumChunks(*w1*, *w2*)

ThreadSafe

Returns truth or falsehood of whether waves *w1* and *w2* have equal number of chunks.

See Also:

[numpnts](#)

SameNumChunksW(*wrefs*)

ThreadSafe

Returns truth or falsehood of whether all waves in *wrefs* have equal number of chunks.

See Also:

[numpnts](#)

SameNumLayers(*w1*, *w2*)

ThreadSafe

Returns truth or falsehood of whether waves *w1* and *w2* have equal number of layers.

See Also:

[numpnts](#)

SameNumLayersW(*wrefs*)

ThreadSafe

Returns truth or falsehood of whether all waves in *wrefs* have equal number of layers.

See Also:

[numpnts](#)

SameNumPnts(*w1*, *w2*)

Returns truth or falsehood of whether waves *w1* and *w2* have equal number of points.

See Also:

[numpnts](#)

SameNumPntsW(*wrefs*)

Returns truth or falsehood of whether all waves in *wrefs* have equal number of points.

See Also:

[numpnts](#)

SameNumRows(*w1*, *w2*)

ThreadSafe

Returns truth or falsehood of whether waves *w1* and *w2* have equal number of rows.

See Also:

[numpnts](#)

SameNumRowsW(*wrefs*)*ThreadSafe*

Returns truth or falsehood of whether all waves in *wrefs* have equal number of rows.

See Also:

[numpnts](#)

SameXscaling(*w1*, *w2*)*ThreadSafe*

Returns truth or falsehood of whether waves *w1* and *w2* have equivalent X scaling.

See Also:

[wave scaling](#)

SatVP(*T_*)

Returns saturation water vapor pressure based on ambient temperature in Celcius.

See Also:

[????](#)

serial2secs(*serialdate*)

Returns Igor date/time value corresponding to the serial date *serialdate*, which is defined as the number of seconds since midnight, January 1, 1970. Serial dates are used by Excel and DAQFactory.

This function is useful in wave assignments.

Examples

```
timestamp = serial2secs( timeW[p] )
```

See Also:

[Date/Time Waves](#), [date2secs](#)

SetBit(*var*, *bit*)

Returns *var* with bit number *bit* set to 1. Bit numbering is zero-indexed.

Details

Since bitwise operators only make sense on integers, *var* is treated as one and an integer is returned.

This is basically a wrapper for the bitwise OR (`|`). It was derived from the example under [Using Bitwise Operators](#).

See Also:

[ClearBit](#), [ShiftBit](#), [TestBit](#), [BitString](#)

ShiftBit(*var*, *by*)

Returns variable *var* after shifting bits *by* number of places. The shift will occur leftwards, increasing *var* if *by* is positive; rightwards, decreasing *var*, if *by* is negative.

Details

Since bitwise operators only make sense on integers, *var* is treated as one. However, it is still possible to receive fractional values when shifting rightwards. [*authors note: find out why*]

This is basically a wrapper for multiplication and division by powers of 2, which has the same effect as multiplication and division by powers of 10 in decimal. It is derived from the example under [Using Bitwise Operators](#).

See Also:

[ClearBit](#), [SetBit](#), [TestBit](#), [BitString](#)

SpecificHumidity(R_{-})

Returns dimensionless specific humidity ratio, defined as mass of water vapor to total mass of system.

See Also:

[wave scaling](#)

SpecificHumidityVP(e_{-} , P_{-})

Returns an approximation of specific humidity.

See Also:

[MixingRatioVP](#), [SpecificHumidity](#)

string2secs(*timestring*, *format*)

Returns Igor date/time value of timestamp represented in string *timestring* using the regular expression in string *format*.

Any double quotes in *timestring* are ignored. The regular expression in *format* follows the conventions of [sscanf](#).

Tips

A suitable regular expression for *format* is probably already available in [TimeRegEx](#).

This function is useful in wave assignments.

Examples

```
Make/D/N=(numpnts(timestampStr)) timestampVal
timestampVal = string2secs( timestampStr[p], TimeRegEx(0) )
```

See Also:

[Date/Time Waves](#), [date2secs](#), [sscanf](#), [TimeRegEx](#)

StringFromMaskedVar(*maskStr*, *inVal*, [, *fixNNwidth*])

Returns *maskStr* after replacing appropriate field codes with values derived from *inVal*.

Details

The string *maskStr* can contain a combination of literal text and zero, one or more field codes described below. Each instance of a field code will be replaced with the indicated value derived from *inVal*. Field codes are case-sensitive.

Field Code

<u>Fixed width</u>	<u>Variable width</u>	<u>Value interpreted from <i>inVal</i></u>
\nn	\n	<i>inVal</i> as integer *
\YYYY		four-digit year
\YY		two-digit year
\MM	\M	month
\DD	\D	day of month
\DDD	\ddd	day of year **not implemented**
\hh	\h	hours, military style
\hhn	\hn	hours, normal style
\mm	\m	minute
\ss	\s	second

***Note:** If optional parameter *fixNNwidth* is not specified, a variable width field will be used instead. If the necessary field width is unknown, it can be found by passing the highest possible value of *inVal* to [MinFieldWidth](#).

Tip

This function was designed to generate an output file name containing timestamp elements but it will create sequential file names too.

Examples

```
print StringFromMaskedVar("test_\YYYY\MM\DD\_hhn\mm", date2secs(1937, 07, 18)+
(14*3600+8*60+37)) // test_19370718_0208 << note: 2PM

print StringFromMaskedVar("test_\YYYY\MM\DD\_hh\mm", date2secs(1937, 07, 18)+
(14*3600+8*60+37)) // test_19370718_1408

print StringFromMaskedVar("\YY\_M\_D\_h\_m\_s.dat", date2secs(1937, 07, 18)+
(14*3600+8*60+37)) // 37_7_18_14_8_37.dat

print StringFromMaskedVar("file_\nn.txt", 4, fixNNwidth=3) // file_004.txt
```

See Also

[MinFieldWidth](#), [ReplaceString](#)

TestBit(var, bit)

Returns the truth (1) or nontruth (0) of whether bit number *bit* is set in *var*.

Details

Since bitwise operands only make sense on integers, *var* is treated as one.

This is basically a wrapper for bitwise AND (&). It was derived from the example under [Using Bitwise Operators](#).

See Also:

[ClearBit](#), [SetBit](#), [ShiftBit](#), [BitString](#)

TimeRegEx(choice)

Returns string containing one of several time stamp regular expressions compatible with [sscanf](#).

<i>choice</i>	<u>Format matching regular expression</u>
0	YYYY-MM-DD hh:mm:ss.sss (ISO, CampbellSci)
1	reserved
2	reserved
3	reserved
4	reserved
5	reserved

See Also:

[string2secs](#), [sscanf](#)

TKE(u_, v_, w_ [, p1, p2])

Returns turbulent kinetic energy derived from orthogonal wind components.

See Also:

[????](#)

UnzipArchive(srcFileStr, destFolderStr, overwrite, flatten)

Unzips archive *srcFileStr* to directory *destFolderStr* and returns semicolon-separated list of unzipped files.

See Also:

[????](#)

UnzipArchivesInList(fileList)

Unzips any archive found in *fileList* to a temp directory, then replaces name of archive in

fileList with list of files inside that archive.

See Also:

[????](#)

UpdateProgressWindow(*name*, *val1*, *val2* [, *msg*, *noKill*])

Updates the named progress window.

See Also:

[????](#)

uvwRotation(*uvwMatrix*, *type*)

rotates waves

References

See Also:

[another topic](#)

VirtualTemp(*T_*, *R_*)

Returns virtual temperature in Celcius given ambient temp in Celcius and water vapor mixing ratio.

See Also:

[????](#)

VirtualTempVP(*T_*, *e_*, *P_*)

Returns virtual temperature in Celcius given ambient temp in Celcius and water vapor pressure and ambient pressure.

See Also:

[????](#)

WaveList2Refs(*wlist*, *makeFreeCopies*)

Returns wave of references to waves listed *wlist*.

See Also:

[????](#)

WaveRefs2List(*wrefs*, *fullName*)

Returns string list of waves in *wrefs*, possibly quoting.

See Also:

[????](#)

WindDir(*Ux*, *Uy*, *azimuth*, *type*)

Returns the direction wind is coming from in the range $0 \leq WD < 360$ based on horizontal components *Ux* and *Uy* as

$$WD = \text{atan2}(-Ux, -Uy) + Vaz$$

where *Vaz* is determined by *type*. If any input values are NAN, then NAN is returned.

Parameters

Ux and *Uy* are variables representing horizontal wind components in an orthogonal space defined according to the variable *type*.

Variable *azimuth* represents the angle, measured (+) clockwise in degrees, between true north and the orientation of the sensor array.

Variable *type* defines the coordinate system of *Ux* and *Uy* to permit the use of different sensor geometries. The angular correction *Vaz* is determined by the value of *type*.

- 0 Use with: Campbell CSAT3, ATI models
This right-handed coordinate system defines +*Ux* as wind into the array, parallel to the sensor boom. Looking into the array along the boom, +*Uy* is oriented leftwards while +*Uz* is upward. *Vaz* = 90
- * No other *type* values are defined yet. It could be expanded as necessary.

References

See Also:

[Another Topic](#)

WindDirMardiaSdev(*Ux*, *Uy* [, *p1*, *p2*])

This is a subtopic.

See Also:

[Another Topic](#)

WindDirScalarMeanSdev(*Ux*, *Uy*, *azimuth*, *flag* [, *p1*, *p2*])

This is a subtopic.

See Also:

[Another Topic](#)

WindDirUnitVectorMean(*Ux*, *Uy*, *azimuth*, *flag* [, *p1*, *p2*])

This is a subtopic.

See Also:

[Another Topic](#)

WindDirVectorMean(*Ux*, *Uy*, *azimuth*, *flag* [, *p1*, *p2*])

This is a subtopic.

See Also:

[Another Topic](#)

WindDirYamartinoSdev(*Ux*, *Uy* [, *p1*, *p2*])

This is a subtopic.

See Also:

[Another Topic](#)

WindSpeed(*Ux*, *Uy*)

This is a subtopic.

See Also:

[Another Topic](#)

WindSpeedScalarMean(*Ux*, *Uy* [, *p1*, *p2*])

This is a subtopic.

See Also:

[Another Topic](#)

WindSpeedScalarHMean(U_x , U_y [, $p1$, $p2$])

This is a subtopic.

See Also:

[Another Topic](#)

WindSpeedScalarSdev(U_x , U_y [, $p1$, $p2$])

This is a subtopic.

See Also:

[Another Topic](#)

WindSpeedVectorMean(U_x , U_y [, $p1$, $p2$])

This is a subtopic.

See Also:

[Another Topic](#)

WindSpeedPersist(U_x , U_y [, $p1$, $p2$])

This is a subtopic.

See Also:

[Another Topic](#)